aMaDEUS

Welcome to the 2013 version of the Amadeus AIR Quick Reference Guide.

The Amadeus Interface Record is a structured record of data that can be sent to another computer system, such as a ticket server or a travel agency back office system.

The Ticketing Amadeus Interface Record, which contains information from the TST and is sent to the ticket server when the user enters TTP, is not part of the scope of this training module.

On-demand Accounting Amadeus Interface Record

TTP/BTK	Creates an accounting Amadeus Interface Record manually.

Starting and Stopping the Queue

BB	Displays the status of the queue.
BASTART	Starts transmission of Amadeus Interface Records on the application queue to back office(untransmitted, non - voided and displayable)
BSSTOP	Stops transmission of Amadeus Interface Records.

Displaying Amadeus Interface Records on the Applications Queue

BD	Displays list of Amadeus Interface Records on the applications queue.
BD07AUG	Displays list of Amadeus Interface Records created on specific date. (Transmitted and Untransmitted)
BL07AUG	Displays list of Amadeus Interface Records created on specific date. (Transmitted only)
BC	Displays count of Amadeus Interface Records on the applications queue. (Untransmitted only)
BI0819926787	Displays Amadeus Interface Record from a list (Transmitted and Untransmitted)
BDTK	Displays incomplete Amadeus Interface Records (Untransmitted only)

Displaying Information about an Amadeus Interface Record

TTZP/0600015345	Display information about an Amadeus Interface Record sequence number on the applications queue.

Manually Transmitting Amadeus Interface Records

BA07AUG	Transmits all untransmitted Amadeus Interface Records on the applications queue, created on a specific date.
BA00498936	Transmits all untransmitted Amadeus Interface Records on the applications queue, created by specific IATA number.
BAPARAX2100	Transmits all untransmitted Amadeus Interface Records on the applications queue, created by a specific office ID.

Retransmitting Amadeus Interface Records

BR07AUG	Retransmits all Amadeus Interface Records created on a specific date.
BR100000014	Retransmits the Amadeus Interface Record with the sequence number you enter.
BR100000014-100000019	Retransmits a range of Amadeus Interface Records, according to the sequence numbers you enter.

Voiding and Restoring Amadeus Interface Records

BV3100000737	Voids an Amadeus Interface Record by sequence number.
BO3100000737	Restores a manually voided Amadeus Interface Record.

Amadeus Interface Record Contents

TTZA	Displays the contents of the latest Amadeus Interface Record generated.
TTZA/SEQ NO **TTZA/3100000737**	Displays the contents of a specific Amadeus Interface Record.
TTZB/SEQ NO **TTZB/3100000737**	This entry displays the back office ticketing Amadeus Interface Record containing the information added by the ticket server (for example, the ticket number). You can use it after a TTP entry.
TTZP/SEQ NO **TTZP/3100000737**	Displays technical information about an Amadeus Interface Record, including the version number.